

# Getting started with Unity and VR


Before you get started, make sure that your VR headset and controllers are properly connected to your workstation. For additional tips on how to get started with the HTC Vive headset, consult the [hardware guide].

In the SteamVR settings, make sure that the **Current OpenXR Runtime** is set to SteamVR instead of Oculus, especially if a VR headset other than the HTC Vive was used on your current computer.

Create a new Unity project using the latest official version. It is beneficial at this stage to check for an updated version, but the rest of this guide will assume you're working with version `2021. 3. 19f1`. Select the **Universal Render Pipeline** as the project type. This format provides the highest graphics fidelity.

Create a new empty scene in your project. Go to Window>Package Manager, choose Packages:Unity Registry from the drop-down menu, then search for **XR Interaction Toolkit** and install the package. The version used in this guide is `2. 2. 0`. From the samples in the XR Interaction Toolkit, import the **Starter Assets**. Install the XR Plugin Manager as well.

Navigate to Edit>Project Settings>Preset Manager. In the Project file explorer, navigate to Assets > Samples > XR Interaction Toolkit > 2.2.0 > Starter Assets, open a preset in the inspector, then click Add to *ScriptName* Default. You should see the preset appear in the preset manager. Repeat this step for all the other presets available in the Starter Assets folder. Make sure that you label the presets for the Left and Right controllers using the filter. If everything is set up correctly, this is what you should see in the Preset Manager:



Navigate to XR Plug-in Management from the Project Settings. Under Plug-in Providers, check the Open XR box, and wait for the scripts to reload. An Open XR tab should appear under Plug-in Management, where you should add the HTC Vive controller profile to the list of interaction profiles. In the OpenXR tab, also make sure that the **Play Mode OpenXR Runtime** is set to SteamVR.

You' re now ready to start building your VR scene in Unity!

Revision #5

Created 22 March 2023 14:26:46 by Matilda Fogato

Updated 11 October 2024 12:04:55 by Matilda Fogato